# MACWA Marsh Futures: Assessment and Mapping of Salt Marsh

## Danielle Kreeger, LeeAnn Haaf & Angela Padeletti

Vulnerabilities to Guide Restoration at the Local Scale

Partnership for the Delaware Estuary

#### Martha Maxwell Doyle & Erin Reilly

Barnegat Bay Partnership







### **Coastal Wetlands**

Abundant Diverse

#### Benefits:


Flood Protection
Water Quality
Fish and Wildlife
Natural Areas
Carbon Capture




### **Coastal Marsh Declines**




- Losing ~1 acre per day in the Delaware Estuary
- Losses due to various stressors





### The Mid-Atlantic Coastal Wetland Assessment



Remote Sensing

Ground-**Truthing** 


Intensive **Studies** 


Monitoring



### Tier 1 – Landscape Census

- NWI, NVCS etc.
- Land Use Land Cover
- Aerial imagery











## Tier 2 – Rapid Assessments

 PDE/BBP/DNREC has assessed the condition of >400 points since 2010 (Mid-TRAM)












### Tier 2 – Rapid Assessments

# Stressor-response relationships vary widely, with lots of interactions

- Hydrology alterations
- Mosquito ditching
- Nutrient loadings
- Fill, Point sources
- Marine debris



Watershed



### Tier 3 – Intensive Studies






### Tier 4 – Station Monitoring


- 11 Stations installed
- Physical, chemical, biological






#### **Interesting Patterns**

Are nutrient loadings affecting ability to keep pace with SLR?








#### **Erosion vs. Accretion**



Majority of marshes are net eroding

from Tier 2 rapid assessments, shoreline metric








### **Two Decline Patterns**



#### Edge Erosion (Horizontal) Interior Drowning (Vertical)






Source: Riter and Kearney 2009

### **Future Challenges**






Most Salt Marshes Cannot Survive When Sea Levels Rise >1 cm Per Year

#### **MACWA Reference Data**


#### 10 cm difference in elevation






Vertical Growth Range of Spartina alterniflora at North Inlet

### Will Tidal Wetlands Keep Pace with SLR?



### Will Tidal Wetlands Keep Pace with SLR?






Plants Have Optimal Growth Ranges



MLW




#### When rate of SLR > rate of (net) accretion ......






... plants can grow taller at first....






#### **But eventually succumb**




### **Elevation Capitol**






### **Elevation Capitol**





## **Coastal Resilience**

→ Coastal Wetland Projects



#### **Post-Sandy Lessons**



Flooding and storm damage was lower adjacent to protective coastal wetlands and dunes



#### **Habitat Benefits**



Table IV-4 Coastal Storm Rick Ma				spament and the little		the first term of the surger
Aggregated Measure Type <sup>1</sup>	Category <sup>2</sup>		Coastal Storm lanagement Fur	ction	Multi-	Resilience
		Flooding	Wave Attenuation	Erosion	Benefits <sup>3</sup>	Adaptive Capacity <sup>4</sup>
Enhanced flood warning and evacuation planning (early						
Deployable floodwalls	STR	Medium	None	None	None	Low
Floodwalls and levees	STR	High	Low	None	Low	Low
Shoreline stabilization (seawalls, revetments, bulkheads)	STR	Low	High	High	Low	Low
oform surge parners					Meaum red	e LOW LOW
Living shorelines	STR/NNBF	Low	Medium	Medium	High	High
Overwash fans (e.g., back bay tidal flats/fans)	NNBF	Low	Medium	High	Medium	High
Reefs	NNBF	Low	Medium	Medium	High	High
Submerged aquatic vegetation	NNBF	Low	Low	Low	High	Medium
Wetlands	NNBF	Low	Medium	Medium	High	High

Of Engineers .

### **Enhancement Tactics**









**Living Shorelines** 





What Tactics?
Where Best?
Successful?





**Sediment Placement** 


#### Sediments are a Critical Feature of the Delaware Estuary












#### **Beneficial Use**

Why Needed?

Marshes need sediments

More sediment is removed from the system by dredging than is replaced via river inputs


Sediment deficits can lead to marsh drowning







#### **Restoration and Beneficial Use**



#### **Investment in Delaware Valley Lags**






Fig. 8.8. Comparison of US EPA federal spending in FY2010 on environmental management and restoration in nine major water bodies in the United States (from Strackbein and Dawson 2011)


Despite Tough Times,...

High Potential for Beneficial Outcomes from Natural Infrastructure Investment

#### **Deciding What to Do Where**



### **Hierarchical Analysis**




Landscape Planning >> Local Project Designs



#### **Planning - Hierarchical Analysis**








#### **Planning - Hierarchical Analysis**






#### **Dredging Layer**



#### Eco Needs Layer



### How to Judge Marsh Impairment?



#### **Observations**


- Wetland impairment can stem from diverse causes
- Pools, pannes, and short vegetation occur in healthy marshes
- Deficits in Elevation Capital (vertical vulnerability) are not always caused by lack of sediments
- Sediment application (TL) can help or harm a marsh
- Sediment impairment and TL opportunities should be identified with care using ecological reference datasets






### Planning - Hierarchical Analysis









### **Marsh Futures Site Assessment**



**Goal**: Develop a field-based rapid assessment method to guide suitable projects that enhance salt marsh integrity


#### **Outcomes:**

- Vulnerability Maps
  - reflect horizontal/vertical processes
- Project Guidance Maps
  - reflect temporal/spatial needs

Local Site Planning

**Verified Conditions** 







Source: Earl, Digitalelobe, Geoffe, Leubed, USBA, USGS, AEX, Getmapping, Aerogrid, 1911, 1917, swisstope, and the GIS User Community

# 2. Desktop Analyses





# 2. Desktop Analyses




## 3. Rapid Field Assessments



# Physical – elevation, slope, erosion, substrate firmness Biological – blade height, light penetration








# 4. Vulnerability Mapping



Use anomalies as weights to adjust elevation scores

#### **Elevation Capital Mapping**


Weighted measures are unitless




# 4. Vulnerability Mapping



**Drowning Risk** 





**Erosion Risk** 




# 5. Project Guidance Mapping



Where will various investments yield greatest outcomes?

What should be the sequence of interventions?



## Results – Vulnerability Maps



#### **Edge Erosion Risk**

Maurice >> Fortescue > Money Island

### **Interior Drowning Risk**

Fortescue > Money Island > Maurice

### **Hydrological Impairment**

Money Island > Fortescue > Maurice



## Results – BMP Maps



#### **Maurice:**

Living Shorelines (aggressive mix needed)

#### **Fortescue**

Thin Layer Sediment (in low spots)
High Marsh Containment
Living Shorelines (to maintain)

#### Money Island


Hydrological Connectivity? (more study needed) High Marsh Containment






### **Planning - Hierarchical Analysis**





#### **Side View**




#### **Top View**



### **Delaware Estuary Living Shoreline Initiative**





### **Recent Living shorelines**












#### **Project Monitoring Linked to MACWA**







# Matts Landing, NJ







## Maurice River, NJ








#### **Living shoreline Monitoring Framework**



#### **Goal-based**







# **Mispillion LS Monitoring**



#### **Core Metrics**

**Shellfish** 

**Vegetation** 

**Sedimentation** 

**Structural Integrity** 

				ESTUZ
Metric Type	Attribute	Goal	Metric	Methods
Core	Physical	Shoreline Stabilization	Elevation Change	RTK
Core	Physical	Shoreline Stabilization	Contiguous	RTK
			Vegetated Edge	
Core	Physical	Shoreline Stabilization	Sediment Capture	RTK
Supplemental	Physical	Shoreline Stabilization	Bearing Capacity	Slide Hammer
Supplemental	Physical	Shoreline Stabilization	Sediment Accretion	Feldspar Marker Horizon
Core	Biological	Ecological Enhancement	Vegetation Robustness	Vegetation Board
Core	Biological	Ecological Enhancement	Vegetation Integrity	Blade Height
Core	Biological	Ecological Enhancement	Extent of Bivalve	Lip Counts
			Communities	Oyster Reef Extent
Core	Biological	Ecological Enhancement	Extent of Bivalve	Shell Bag
			Communities	Recruitment
Core	Biological	Ecological Enhancement	Inhibition of "Critter"	Presence/Absence of
			Movement	Trapped "Critters"
Core	Chemical	Prevailing Environmental Conditions	Temperature	YSI
Core	Chemical	Prevailing Environmental Conditions	Salinity	YSI
Core	Other	Structural Integrity of Materials	Coir Logs	Observation
Core	Other	Structural Integrity of Materials	Coir Mats	Observation
Core	Other	Structural Integrity of Materials	Shellbags	Observation
Core	Other	Structural Integrity of Materials	Hardened Structures	Observation
Core	Other	Disturbance	Anthropogenic	Observation
Core	Other	Disturbance	Wildlife	Observation
Core	Other	Photo Documentation		Camera

### Statistical Approach = BACIR



#### Before - After - Control - Indicator - Reference

Marsh Treatments

Oyster Breakwater



Controls

Reference = nearest MACWA station





### **Mispillion LS Results - Physical**




#### **Did Sediment Collect?**

#### Yes

Treated areas gained elevation

Untreated areas continued to lose elevation








# **Mispillion LS Results - Biological**



#### **Did Plants Survive?**

Yes







### **Mispillion LS Results - Biological**





#### **Did Shellfish Colonize Structures?**

#### Yes

Good oyster recruitment in 2014, better in 2015

Mussel data still being analyzed






### **Next Steps for Marsh Futures**



- Refine Metrics to reflect different types of vulnerabilities
- Streamline field efforts to more rapidly assess sites or expand to larger areas






# Conclusions



- Tidal wetlands are vital for coastal resilience in the Delaware Estuary region, but are in decline
- Well-designed restoration projects are needed and should address specific ecological impairments
- Marsh Futures is an example method for providing project guidance using ecological datasets
- Beneficial use of dredged sediments can help address certain types of marsh impairment if carefully deduced and matched to ecological needs; but there is risk of harm
- Most tidal wetland decline is due to edge erosion, and restoration of lost and degraded marsh edges may offer greater bang for buck compared to platform elevation





#### **For More Info**

PDE Report No. 15-03. Marsh Futures: use of scientific survey tools to assess local salt marsh vulnerability and chart best management practices and interventions. <a href="http://delawareestuary.org/sciencereports">http://delawareestuary.org/sciencereports</a>

